

# MAGic Keystrokes

**Note:** By default, the **MAGic Key** is the **CAPS LOCK** key on your keyboard.

## General

Description	General Keystrokes
Start MAGic	<b>CTRL+ALT+M</b> (default keystroke – can be changed using the Startup Wizard)
Run Script Manager (Only available for MAGic Pro Scripting Edition)	<b>INSERT+0</b>
Minimize/Restore the MAGic User Interface	<b>MAGic Key+U</b>
Pass Through Key	<b>MAGic Key+3</b>
Refresh Screen	<b>MAGic Key+ESC</b>
Open MAGic Context Menu	<b>MAGic Key+APPLICATION Key</b> or <b>MAGic Key+RIGHT MOUSE BUTTON CLICK</b>

## Magnification, Views, and Enhancements

Description	Magnification, Views, and Enhancements Keystrokes
Increase Magnification	<b>MAGic Key+NUM PAD PLUS</b> or <b>CTRL+EQUALS</b> or <b>MOUSE WHEEL UP</b> (scroll wheel up or away from you)

Description	Magnification, Views, and Enhancements Keystrokes
Decrease Magnification	<b>MAGic Key+NUM PAD MINUS</b> or <b>CTRL+DASH</b> or <b>MOUSE WHEEL DOWN</b> (scroll wheel down or towards you)
Magnification Toggle On/Off	<b>MAGic Key+DELETE</b>
Toggle between 1x Magnification and Current Magnification	<b>MAGic Key+SHIFT+DELETE</b> or <b>MAGic Key+MOUSE MIDDLE CLICK</b> (press down on scroll wheel)
Switch to Next Magnified View	<b>MAGic Key+NUM PAD SLASH</b>
Switch to Previous Magnified View	<b>MAGic Key+SHIFT+NUM PAD SLASH</b>
Toggle Color Enhancements On/Off	<b>MAGic Key+F12</b>
Toggle Cursor Enhancements On/Off	<b>MAGic Key+F8</b>
Toggle Mouse Enhancements On/Off	<b>MAGic Key+F4</b>

## Panning and Screen Movement

Description	Panning and Screen Movement Keystrokes
Pan Right	<b>MAGic Key+RIGHT ARROW</b>
Pan Left	<b>MAGic Key+LEFT ARROW</b>
Pan Down	<b>MAGic Key+DOWN ARROW</b>
Pan Up	<b>MAGic Key+UP ARROW</b>
Increase Speed during Panning	<b>NUM PAD PLUS</b>

<b>Description</b>	<b>Panning and Screen Movement Keystrokes</b>
Decrease Speed during Panning	<b>NUM PAD MINUS</b>
Move to Left Edge of Screen in Magnified View	<b>MAGic Key+HOME</b>
Move to Right Edge of Screen in Magnified View	<b>MAGic Key+END</b>
Move to top of Screen	<b>MAGic Key+PAGE UP</b>
Move to Bottom of Screen	<b>MAGic Key+PAGE DOWN</b>
Move to Beginning of Next Line	<b>MAGic Key+ENTER</b>

## Tracking

<b>Description</b>	<b>Tracking Keystrokes</b>
Tracking Toggle On/Off	<b>MAGic Key+R</b>
Move View to Mouse Pointer	<b>MAGic Key+NUM PAD 5</b>
Move View to Cursor	<b>SHIFT+MAGic Key+NUM PAD 5</b>
Tether Mouse to Display	<b>CTRL+INSERT+NUM PAD MINUS</b>

## Cursor Movement

<b>Description</b>	<b>Cursor Movement Keystrokes</b>
Route Cursor to Mouse	<b>INSERT+NUM PAD PLUS</b>
Route Mouse to Cursor	<b>INSERT+NUM PAD MINUS</b>

## Locator Mode

Description	Locator Mode Keystrokes
Start Locator	<b>MAGic Key+F10</b>
Stop Locator and Move to Selected Area	<b>ENTER</b>
Stop Locator without Moving the Magnified Area	<b>ESC</b>
Move Left	<b>LEFT ARROW</b>
Move Right	<b>RIGHT ARROW</b>
Move Up	<b>UP ARROW</b>
Move Down	<b>DOWN ARROW</b>
Move to End of Line	<b>END</b>
Move to Beginning of Line	<b>HOME</b>
Move to Top of Screen	<b>PAGE UP</b>
Move to Bottom of Screen	<b>PAGE DOWN</b>

## Quick View Frame

Description	Quick View Frame Keystrokes
Toggle Quick View Frame On/Off	<b>MAGic Key+Q</b>
Set upper left corner of frame	<b>MAGic Key+LEFT BRACKET</b>
Set lower right corner of frame	<b>MAGic Key+RIGHT BRACKET</b>
Create frame around current dialog box option	<b>MAGic Key+LEFT BRACKET</b> twice quickly
Open Quick View Manager	<b>MAGic Key+9</b>

# Speech

Description	Speech Keystrokes
Silence Current Speech	<b>CTRL</b>
Enable/Disable Speech	<b>MAGic Key+F3</b>
Voice Profiles	<b>MAGic Key+F11</b>
Set Screen Echo	<b>INSERT+S</b>
Select Verbosity Scheme	<b>INSERT+ALT+S</b>

# Document and Text Reading

Description	Document and Text Reading Keystrokes
Read All from Location (Say All)	<b>INSERT+DOWN ARROW</b> or <b>MAGic Key+LEFT MOUSE BUTTON CLICK</b> or <b>MAGic Key+SPACEBAR</b>
Alternate Say All	<b>INSERT+ALT+DOWN ARROW</b> or <b>MAGic Key+ALT+LEFT MOUSE BUTTON CLICK</b> or <b>MAGic Key+ALT+SPACEBAR</b>
Read Active Window (reads from the beginning of document window)	<b>MAGic Key+SPACEBAR</b> (twice) or <b>INSERT+DOWN ARROW</b> (twice)
Say Currently Selected Text	<b>MAGic Key+CTRL</b> or <b>INSERT+SHIFT+DOWN ARROW</b>
Say Current Character	<b>NUM PAD 5</b>
Say Current Word	<b>MAGic Key+ALT</b> or <b>INSERT+NUM PAD 5</b>
Spell Current Word	<b>MAGic Key+ALT</b> (twice) or <b>INSERT+NUM PAD 5</b> (twice)

<b>Description</b>	<b>Document and Text Reading Keystrokes</b>
Next Word	<b>INSERT+RIGHT ARROW</b>
Prior Word	<b>INSERT+LEFT ARROW</b>
Select Next Word	<b>INSERT+SHIFT+RIGHT ARROW</b>
Select Prior Word	<b>INSERT+SHIFT+LEFT ARROW</b>
Say Current Line	<b>MAGic Key+L or INSERT+UP ARROW</b>
Next Line	<b>DOWN ARROW</b>
Prior Line	<b>UP ARROW</b>
Read to Cursor	<b>INSERT+HOME</b>
Read from Cursor	<b>INSERT+PAGE UP</b>
Say Current Sentence	<b>MAGic Key+S</b>
Next Sentence	<b>MAGic Key+CTRL+S</b>
Say Current Paragraph	<b>MAGic Key+P</b>
Read Column from Current Position	<b>MAGic Key+C</b>
Say Contents of Clipboard	<b>MAGic Key+X</b>

**Note:** When using the document and text reading commands, if you move the mouse MAGic reads from the current location of the mouse pointer. If you move the insertion point, MAGic reads from the location of the insertion point.

## Dialog Box Reading

<b>Description</b>	<b>Dialog Box Reading Keystrokes</b>
Say Title Bar	<b>MAGic Key+T or INSERT+T</b>

<b>Description</b>	<b>Dialog Box Reading Keystrokes</b>
Read Bottom of Window	<b>INSERT+PAGE DOWN</b>
Say Top Line of Window	<b>INSERT+END</b>
Say Default Button in Dialog Box	<b>INSERT+E</b>
Say Window Prompt and Text	<b>MAGic Key+TAB</b> or <b>INSERT+TAB</b>
Say Current Access Key	<b>SHIFT+NUM PAD 5</b>

## Table Reading

<b>Description</b>	<b>Table Reading Keystrokes</b>
Say Current Cell	<b>ALT+CTRL+NUM PAD 5</b>
Cell to Right	<b>ALT+CTRL+RIGHT ARROW</b>
Cell to Left	<b>ALT+CTRL+LEFT ARROW</b>
Cell Below	<b>ALT+CTRL+DOWN ARROW</b>
Cell Above	<b>ALT+CTRL+UP ARROW</b>
First Cell	<b>ALT+CTRL+HOME</b>
Last Cell	<b>ALT+CTRL+END</b>
First Cell in Column	<b>ALT+CTRL+SHIFT+UP ARROW</b>
Last Cell in Column	<b>ALT+CTRL+SHIFT+DOWN ARROW</b>
First Cell in Row	<b>ALT+CTRL+SHIFT+LEFT ARROW</b>
Last Cell in Row	<b>ALT+CTRL+SHIFT+RIGHT ARROW</b>

## Typing Echo

Description	Typing Echo Keystrokes
Cycle through Indicate Capitalization options	<b>MAGic Key+F2</b>
Cycle through Typing Echo Unit options	<b>INSERT+2</b>

## Mouse Echo

Description	Mouse Echo Keystrokes
Mouse Echo Toggle	<b>MAGic Key+M</b>

**Note:** Toggling the mouse echo rotates between speak lines, speak words, and mouse echo off.

Some actions in MAGic do not have hot keys assigned. You can define hot keys for these features from within the **Keyboard Manager** dialog box.

## Multi-Monitor

Description	Multi-Monitor Keystrokes
Switch focus between monitors	<b>MAGic Key+SHIFT+D</b>
Move the current application or window in focus to the monitor on the right or the left (Windows 7).	<b>WINDOWS Key+SHIFT+RIGHT ARROW</b> or <b>WINDOWS Key+SHIFT+LEFT ARROW</b>
View Lock. Press and hold and drag mouse to move the mouse pointer between screens without scrolling any screen content.	<b>MAGic Key+SHIFT</b>